

Manual 2020

General description	3
Installation of the software	4
Licensing of the software	6
First steps	7
Keyboard settings	8
Versions of the software	9
DEMO Version	10
FULL Version	11
menu bar	12
Title	13
Title search	14
search for title A-Z	
search form tilt-part	17
search for keywords	
Title new	20
Title edit	
Title delete	24
Title copy	25
PDF synchron	
SETs	
random title	
Titelautomatik	
Program title automatic	
MIDI settings for titelautomatic	
Titlelist	
Titlelist new	
Titlelist delete	41
Titlelist change	42
Sheet music in PDF format	
Scan in scores	
Show scores	
Video	
PRESETs	
PRESET copy	
Service settings	
MIDI settings	
program update	
equipment	
footswitch	
bluetooth	
USB	
system requirements	
Tips und Tricks	
Use of internal help	
right mousekey	
remote maintenance	
Enter comments in sheet music	

The idea:

Stop lup music books or folders to the show. All notes in the computer, and when calling up and displaying a sheet music file it is also best to automatically set the keyboard correctly to the title.

ATMObyte® TYROS-Editionis a complex software, with an unlimited number of titles and the associated notes or texts in <u>PDF format</u>. The titles can be distributed to any number of playlists. Titles can be assigned to 12 different <u>set's</u> and the desired set can be activated with one click.

For each title, a sound file in mp3 format can be deposited and played as required. For each title, a video file (mp4) can be stored and played on a second monitor or projector as needed.

> With the scanning function integrated in *ATMObyte® TYROS-Edition*, existing paper notes can be scanned directly. The correct assignment and saving in <u>PDF format</u> are automatic. Of course, already existing PDF files can be used. Calling a title not only displays the corresponding notes, but the title-related registration of the connected **keyboard** is called automatically.

> > The software runs under all <u>Windows systems</u>.

Mac systems require the installation of VMware Fusion beforehand. If a tablet computer is used, the software automatically adapts to the position of the tablet. When used vertically (portrait), the display automatically switches to 1-sided display, so that the sheet of music is displayed on the entire display. **ATMObyte® TYROS-Edition** but only start when the desired position of the display is done.

1.1 Installation from CD

After inserting the CD into the computer, the installation program starts automatically. If this does not happen please start the file *InstallYGE.exe* on the CD with a double-click.

1.2 Installation of the download version

In the download version, the program is automatically installed.

The following menu options are now available:

install program for TYROS - Edition ATMObyte TYROS-Edition
ATMObyte TYROS - Edition
install
USB - driver
YAMAHA 32bit YAMAHA 64bit
manual 🏭
exit×

The *ATMObyte® TYROS-Edition* installation routine installs the program on your computer. The installation directory can be chosen freely and is preset to **C: **.

Installation is not possible in the directories **C: \ Programs** and **C: \ Programs (x86)**. These directories are systemically important. An installation would only require a change in the registry be possible and that should be avoided. Only the folder *ATMObyte*® *TYROS-Edition* with all files belonging to the program will be copied to the hard disk and no changes are made to the system or the REGISTRY.

During the installation this message can come from Windows Defender,



but that has to do with Microsoft and their caution and not with problems or dangers of the software itself.

Of course, Windows knows neither the program nor the manufacturer, so security is important first. You also get this message when installing many other programs.

The installation is carried out by clicking on **More information** and then on **Install anyway**.

When first started, the software starts as a <u>DEMO version</u>. To license the software, from the <u>DEMO version</u> to make a <u>full version</u>, the entry of a license code is necessary.

The entry is made in the menu item SERVICE under license.



For the creation of the license code the serial number is always necessary.

First steps

After the software is installed, it can be started.

At the first call the software starts as DEMO version. In the DEMO version the software can be extensively tested.

The only limitations are that the notes are overwritten with **DEMO**.

All other, can be used without restrictions.

If a <u>license code</u> is available, the software can be registered with this code and is a <u>full version</u>.

If you want to call up the registration of the keyboard for the title you are calling, so the keyboard must first be set once to the correct <u>MIDI channel</u>.

This channel is specified by **ATMObyte® TYROS**- **Edition** and can be changed under <u>Service-> Settings</u>. When installing **ATMObyte® TYROS-Edition** for the first time, this is channel 16.

Keyboard settings

To use the registration call of the connected keyboard just change the <u>MIDI setting</u> of the keyboard as follows:

If the MIDI channel 16 is used, the following settings apply to the keyboard: MIDI IN Channel 16

DEMO version

At the first call the software starts as DEMO version. In the DEMO version the software can be extensively tested.

The only limitations are that the notes are overwritten with **DEMO**.

All other functions can be used without restrictions.

FULL version

In the full version, is after entering a correct license code, all functions listed in the description are executable. The coverage of the notes with **DEMO** in the DEMO version is no longer visible.

menu bar

The individual functions of *ATMObyte*® *TYROS*-*Edition* can be called up via the buttons in the menu bar.

itlelist Service PRESETS With program the ATMObyte® TYROS-Edition can be stopped With *title* a title can be used to create a title a title will be deleted a title will be copied a title will be rename With *Titlelist* a new titlelist can be create a titlellist will be deleted a titlellsit will be renam Service switches to the settings area of the program and important program properties can be changed. With **PRESETs** the 20 available PRESETs are called. These can be edited and / or played. Keyboard on / off displays or hides an on-screen keyboard. With the *country flags* the language of the program can be changed. The switch Software Control affect the control behavior of ATMObyte® TYROS-Edition. If the switch Software Control is deactivated, the registration will be made for a title call the akkordeon does not change. Only the notes are displayed. This allows playing a variety of titles with the same registration of the akkordeon.

Title

A title is an entry in one of any number of <u>titlelists</u>. The number of titles in a <u>titlelist</u> is unlimited.

A title is called by its name.

This name also assigns the notes and any existing mp3 files or video files to the title.

These files must be named exactly as the title. If the <u>title</u> is Yesterday, the corresponding sheet PDF is Yesterday.pdf. The mp3 file Yesterday.mp3 and the video file Yesterday.mp4.

If **ATMObyte® TYROS-Edition's** internal <u>scanning</u> program is used to scan the scores, this will automatically generate the name of the <u>PDF file</u> correctly and the sheet music is stored in the directory. \ PDF \ Display1. The selection of a title can be done in different ways.



Mauscrollwheel The scroll wheel of the mouse scrolls through the title list. arrow keys Use the arrow keys to the left of the title list to maneuver. OnScreenKeyboard

> The title is selected using the screen keyboard below the title list. The on-screen keyboard can be displayed and hidden as desired. This is done by means of the keyboard on / off button .

keyboard on/off

									2.1			3
	×	5	D	F.	2	H	1	R E 5 8 98	- 4	5	5	- 1 -
50	Y	X	C	7	B		I	Leetaste	C L	2	3	6 kr

Seite 14 von 68



All functions can be performed by mouse or with a touchmonitor by finger.

Searching for a <u>title</u> using the on-screen keyboard or the PC keyboard can be done after the <u>title</u>, is alphabetically or it can also be searched for a letter sequence in the <u>title</u> name. To do so, select Search for below Title bar or Title content below the menu bar.

	search for	
• title A-Z	\odot title part	○ keywords
		Set: all songs

If the <u>title</u> search is set to the beginning of the title, the first title that starts with **B** is selected by entering the letter **B**. If one enters now the letter **A** one ends up with the first title with the initial letters **BA**, e.g. Baker Street. If you enter an **R** and there is no title with the initial letters **BAR** in the title list, the first title is immediately marked with the initial letter **R**. During the title search for content, the entered letter sequence does not have to be at the beginning of the <u>title</u>, but may be somewhere in the title name.

All titles are then displayed in which the entered letter sequence exists.

If you enter e.g. If you enter the word ROSE, all titles appear with this letter sequence.



When searching for keywords, the middle touch panel displays all the keywords used in the program.

Title	Bank	Register	Set1	Set2	keywords
!Volker	0	0			Jackl
's Boarische Bier	87	6			Jazz
16" und 8" Chor, minim. verstimmt	81	11			Club
16"er mit Cassotto	81	6			
A Rindvieh	87	5	X		Reinhold
A Rindvieh mag koa Bier	87	4			Frankreich
A weißes Blatt 'l Papier -Relax-	0	0			Stimmung
A Whiter Shade Of Pale	5	7	X		Oldie
Abendglocken	69	14			Grenzland
Abends in der Taverne	85	10	X		Bank
Aber bitte mit Sahne	17	11	X		Unterhaltung
Aber böhmisch muss es sein	72	10			Roider
Aber der Novak lässt mich nicht verkomme	1	1			
Aber Dich gibt 's nur einmal für mich	1	13	X		
Aber heidschi, bumbeidschi	55	5	X		
Abschied ist ein scharfes Schwert	6	2	X		
Abschied ist ein scharfes Schwert 2	6	2	X		
Adalita -Ikarus Showorchester-	72	6			

If you now use the keyword Frankreich, the title display shows all <u>titles</u> to which this keyword has been assigned.

Title	Bank	Register	Set1	Set2	keywords
!Volker	0	0			Jackl
Akkordeon, Akkordeon (Am) -Alexandra-	10	6			Jazz
Alles fürs Vaterland (F) -Musettewalzer-	7	3			Club
Alt & Musette	54	10			
Cestsibon (B++)	39	10			Reinhold
Chanson d´Amour (F)	8	6			Frankreich
Das hab ich in Paris gelernt (C) -Chris	36	12			Stimmung
Ganz Paris träumt von der Liebe	7	1			Oldie
Hinter den Kulissen von Paris -Alois-	86	10			Grenzland
Klari & Musette	54	11			Bank
Lied von Paris (G)	50	10			Unterhaltung
Mademoiselle de Paris (Dm+D)	50	11			Roider
Mademoiselle de Paris (F)	52	7			
Mademoiselle de Paris (Gm)	66	2			
Melodie d´Amour -Calypso Stil-	87	1			
Moulin Rouge	46	7			
Musette (Cm)	37	12			
Musette + Saxophon	21	2			

With title-> new in the menu bar a title is added to the current title list, or by clicking on the *Insert key*. The input mask then opens.



<u>title</u> keywords	
	keywords & ^ (C)
Bank 0 Register 0 Button - direction	(D) (Dm) (F) (G) (Gm+G) - -instrumental- -Mix- -Siggi-
Querformat	3 30 52 Abba Abend, Akk. Al Albers
★ cancel scores Scan √ Sav	Alexander

The most important input is the title name. Without this input can not be saved.

For each title keywords can be assigned. After this, the title can then be searched.

The keywords already used in the program are listed in the list of tags and can be accepted with a *double-click*.

If a new keyword is entered, it is automatically added to the keyword list.

Seite 20 von 68

Keywords can be the artist, the composer, the genre, the key, the epoch, and so on.

The entries for registration have 2 values.

- 1. the registration bank
- 2. the registration memory to be started with.

The <u>Scan Scores</u> button allows scores to be scanned directly from the program and the title.

This feature is detailed in <u>Scanning Scores</u>.

Title> Edit in the menu bar opens the selected title for editing. It then opens the same mask as when creating a new title. There are only the title name and all entered parameters of the title available.

The editing of a title can also be done by a click with the right mouse button on the title name.



<u>Titel</u>		
Fly Away		
<u>Schlagwörter</u>		
		keywords
Bank 8 Register 1	Button - Richtung	& ^ (C) (D) (Dm) (F) (G) (Gm+G)
Querformat		3 30 52 Abba Abend, Akk. Al Albers
Xabbrechen Noten scannen	√ speichern	Alexander Alexandra Alexandre
		< >

The most important input is the title name. Without this input can not be saved. For each title keywords can be assigned. After this, the title can then be searched. The keywords already used in the program are listed in the list of tags and can be accepted with a *double-click*. If a new keyword is entered, it is automatically added to the keyword list.

Keywords can be the artist, the composer, the genre, the key, the epoch, and so on.

The entries for registration are described in Registration.

The <u>Scan Scores</u> button allows scores to be <u>scanned</u> directly from the program and the <u>title</u>. This feature is detailed in <u>Scanning Scores</u>. With Title-> delete in the menu bar a title can be deleted. Deleting can also be done by clicking on the *Del key*. When deleting, only the entry in the title list with all settings is removed.



Should the title really be deleted?											
Alice											
X and											
🗙 no	🥪 yes										

After confirming the delete request, the title will be permanently removed from the title list.

The **Title-> Copy** function in the menu bar allows you to copy a title.



The title then appears with the same name and the extension **COPY**.

A women in Love	1	*	*	
 Alexis	139	*		
Alhambra	262	*		
Alice	114	*		*
 Alice Copy	114	*		*
All About That Bass	140	*	*	
 All By Myself	169	*		
All I Want For Christmas	115	*		

PDF synchron



This feature finds the PDF files in the **PDF\Display1** directory, that are not present in the current playlist. If you want to create a title from a displayed PDF, just click on the PDF and in the current title list a title with the name of the PDF is created.

Via **print list** a list with all PDF files in the directory **PDF\D isplay1** is printed out. The PDF's for which a title exists in the current playlist are marked with an **X**.

ListPDF

PDF-fil	es not	in titel	list ((495)
---------	--------	----------	--------	-------

E.		1		l		1	i	í	i																	
11		I	١	l		I	I		ŀ	ŀ	٦	i	•		1	1	1	^	1	١	1	L		1	ł	
18	J	ł		ļ	L	I	I		L		1	h	ſ	ſ	1	I				I			U	ſ		
181	٠			1	•	1	1	1	1		1		2		1		1		1	1		1	ĩ			

Albeity					
Anita					
B6_13-Ungarischer Tanz Nr. 6-Brahms					
B6_14-The Entertainer					
B6_15- Click for insert in titlelist					
B6_16-C nor mendet bach					
B6_17-Scarborough Fair					
B6_18-In mir klingt ein Lied					
B6_19-See you later, Alligator					
B6_20-Musik liegt in der Luft					
B6_21-Humoreske-Dvorak					
B6_22-Autumn in Romania					
B6_23-Csardas					
B6_24-Sambita y Cantabile					
Banks of Ohio					
Banks of the Ohio					
Beer Beer Beer					
Bella Ciao					
Blanket on the Ground					
Blanket on the Ground					
	×				
<	>				
Print List	× Cancel				

^

SETs are the selections for the playlist, which are located on the right edge of the screen. The title list can be limited by the **SETs** to certain selection ranges



To assign a title to a **SET**, a star is generated for this title in the matrix for the relevant **SET** with a click. A further click on this field deletes the marking

Titel	Register	Set1	Set2	Set3	Set4	Set5	Set6	Set7	Set8	Set9	Set10	Set11	Set1
!aaaa	1												
!Test 3 Seiten	1	*											
54 74 90 Stiller	478	*		*									
7 Tage Sonne	237	*		*			*						
8 Seiten	1	*	*				*						
A women in Love	1	*	*				*						
Alexis	139	*					*						
Alhambra	262	*											
Alice	114	*			*	*							
Alice Kopie	114	*			*	*							
All About That Bass	140	*	*										
All By Myself	169	*											
All I Want For Christmas	115	*											
All my loving	115	*							*				
All shook up	120	*				*							
All you need is love	197	*											
Alles im Griff	457	*							*				
Aloha Hea	472	*											

If you now click on a **SET** on the right side of the screen, only the titles appear in the <u>title list</u>, which have been assigned to the **SET**.

The SET selection can also be made by clicking on the corresponding column header.

Set1	Set2	Set3	Set4	Set5	Set6	Set7	Set8	Set9	Set10	Set11	Set12
*											
*		*									
*		*			*						
*	*				*						
					-						

The names for the **SETs** can be changed by clicking with the right mouse button on the **SET** name. If no name is entered for a **SET**, the name is automatically entered as the name.

random title

By clicking on random title



an arbitrary title is selected and called up from the title list.

titleautomatic

Titleautomatic means: For each title, tactical and one-eighth measures are defined be, e.g. Change Registration Memory, switch MAIN or OTS, turn sheet music and much more .. The automatic for a title can be switched off at any time. The programming of the titleautomatic is started with a click on the button automatic.



Now, the title and the programming interface previously marked in the title selection are displayed.



The score will appear on the real screen half. In order to determine when which action should be triggered, the note picture must be visible for counting the bars.



If not already done, the time signature will first be selected for the <u>title</u>. Then a new action can be created with **New action**.

loha Hea		<u>Taktart</u>
akt/Achtel	Aktion	4/4 ~
11 .	Neue Aktion auswählen	~
1 2 3 4 5 6 7 8		
X Löscher	Neue Aktion	J Speichern

Then the clock and the eighths desired for the action are set, e.g. Clock 1 and Achtel1. Seite 33 von 68



And finally choose the action, in our case the Intro3.

<u>Titel</u> Aloha Hea		
		<u>Taktart</u>
Takt/Achtel	Aktion	4/4 ~
1 1	INTRO3	
×	A market	1
X Löschen	Neue Aktion	Speichern

Our first action is programmed: INTRO 3 is triggered in CLOCK 1 on the first axis. Now more actions can be added and then save the whole thing and done.

The following actions are available:

Registration Memory 1	MAIN D	OTS 1
Registration Memory 2	FILL BRAK	OTS 2
Registration Memory 3	ENDING1	OTS 3
Registration Memory 4	ENDING2	OTS 4
Registration Memory 5	ENDING3	MODULATION(ALT) RIGHT1
Registration Memory 6	STYLE PAUSE 1 TAKT	MODULATION(ALT) RIGHT2
Registration Memory 7	STYLE PAUSE 2 TAKTE	MODULATION(ALT) RIGHT3
Registration Memory 8	STYLE PAUSE 3 TAKTE	SUSTAIN
INTRO1	STYLE STOP	BASS HOLD
INTRO2	FADE IN/OUT	VOCAL HARMONY





The programming for a title can also be exported. The destination directory can be chosen freely, e.g. a USB stick. The created file has the title name and the suffix .aut. Likewise, the title programming available in an export file can also be imported.



With **exit** the programming interface is closed again.

If an automatic program is programmed for a <u>title</u>, a light blue field is displayed in front of the <u>title</u> in the <u>title lis</u>t.



If you now click on this light blue field, it will be dark red and the automatic for this <u>title</u> is active. The automatic starts when TYROS the Style is started.



In order to use all functions of the title automatic, the TYROS must be adapted to the MIDI settings.
MIDI settings für titleautomatic

The MIDI settings for using titleautomatic are described in the MIDI Settings.

Tilellist

A title list can contain an unlimited number of titles.

Any number of titlelists can be created.

At the first program start, the playlists are **Titelliste00-DEMO** set with 20 titles as DEMO playlists.

If title ists are created, they start with the number 21.

Creating a new titlelist is done in the menu bar with titlelist-new.



An input window opens and the name of the new list can be assigned.

Enter a short name (for example Chris	
cancel	next

The self-created titlelists start with the number 20 and are numbered consecutively, e.g. Titlelliste20 Christmas.

If the new title list is successfully created, this is confirmed.

i	crea	Titelliste20 teted you can use	
		OK	

Via *titlelist-> Rename* in the menu bar, the name of the titlelist can also be changed later.



	change new delete rename	i I I
Kurzbeze	ichnung von: Ti Tyros5	telliste05
Neu	e Kurzbezeichn	ung:
Tyros5		
abbrech	en übe	ernehmen

Deleting a title list is done with *titlelist-> delete* in the menu bar.



By clicking on the corresponding titlelist and confirming the deletion query, the selected titlelist is deleted.



The active titl list and the DEMO Titellliste00 can not be deleted !!!

The change between the existing title lists is done by means of *title list-> change* in the menu bar.



In the opening selection window all available titlelists are listed. Click on the desired titlelist to activate it immediately.

🖻 titellist change	\times
<u>Active Titlellist</u> <u>Titelliste05 - Tyros5</u>	
Titelliste00 - DEMO - TYROS4	^
Titelliste01 - Pa3X	
Titelliste02 - Tyros2	
Titelliste04 - Tyros4	
Titelliste05 - Tyros5	
Titelliste08 - Rolf	
Titelliste09 - Gesangbuch	
Titelliste10 - Neue Liste	
Titelliste11 - Gesamt GENOS	
Titelliste12 - Gesamt Tyros 5	
Titelliste13 - BUGARI	
Titelliste14 - TestNI	
Titelliste15 - Test	~

Each title includes a score PDF. This is located in the folder **PDF\Display1** or **PDF\Display2**.

If notes are already available in PDF format, they can be used. They just need to be copied to the directory **PDF\Display1** or **PDF\Display2**.

By default, the notes from the **PDF\Display1** directory are used. However, if activated under *SERVICE* **Display2**, the notes from the **PDF\Display2** directory are used. In this way the titles can be assigned different note images.

Service	
settings Lizenz	
PDF Manual	
help F1 Display2 🛛	

The PDF file must match the title name exactly,

So for the *title Red Roses*, the PDF file *Red Roses.pdf* must be called.

If printed notes are available for the title, they can be scanned in via the integrated <u>scan function</u>. To do this, a scanner must be connected to the PC via USB. If printed notes are available for the title, they can be scanned in via the integrated scan function. To do this, a scanner must be connected to the PC via USB.

<u>Titel</u> Fly Away	
<u>Schlagwörter</u>	
Bank 8 Register 1	Button - Richtung
Querformat 🗆	S Richtung
X abbrechen Noten s	cannen 🗸 speichern

The next window determines whether the scanned notes stored in **PDF/Display1** or in **PDF/Display2** ..

A Not	ten Scannen	_	_	\times
	Scannen Display1		Scanı Displ	
	Abb	rech	ien	

Click on Scan Display1 or on Scan Display2 to start scanning.

The optimal setting of the scanner must be made in the scan dialog and depends on the scanner. If the scanner shows 2 scanner drivers, please use the driver that starts with WIA.

Select source	×
Live! Cam Chat HD VF0790 EPSON Perfection V37/V370 Lexmark S300-S400 Series TWAIN Canon MF8200C Series Canon MG5100 ser CanoScan LiDE 120 WIA-EPSON Perfection V37/V370	
ОК	Cancel

After the scanning process, the notes are automatically stored in the correct folder and can be immediately called up and displayed with the title.

> There are no further entries like name of the <u>PDF file</u> or number of pages of notes necessary for the <u>title</u>, since this is done automatically by the program.

By clicking on the title name or pressing the *ENTER key* the sheet music for the title is displayed.

Tico Tico Tico Tico Rhytmus: Samba Tempo: 100 Seite 2/3 Rhytmus: Samba **E**7 Am Dm ╵╻╻╞╽╺┝╵╻╻ المراجع المردا المؤونية المناز المرواج المراجع المراجع المراجع المراجع المراجع المراجع المراجع المراجع F7 ╔╗┙╒┈┍╖╸╔╢╺┶┶┶╗╗┙┊╴┊╻╗╸╸╵╻╗╸ 011140 Am 0 7 1 1 1 - 1 لألمام F₿07 ا م م م م م له له ا به م م « له له الته الته له الته م « له ا م م م م م م م هذا ملام م 🤊 م ما م ارز 🗸 م 🖓 م ا ملام 🗸 ال^{##} | مالم حدث ألا وي حدث في أو و و مام م E7 • • • • • • ا مام ۲۰۰۰ با درو درار المال کر او در ۲۰ ۱۸ در ۱۸ در در ۲۰ در د 6¢

By clicking on the title name or pressing the ENTER key In this case, it is a title with several Notidenitenamae.



you go back to the title selection.

If the PDF file has multiple pages and scrolling is necessary, the required buttons for turning pages are visible.

Turning pages can also be done with a *footswitch* or with a fingerwash (touch screen).

If an mp3 file is available, it can be started via the *mp3 button*. This button is only visible if an mp3 file belonging to the title exists.



Whether the control button should appear to the left or right of the notes, can be set under **SERVICE-> Settings** by clicking on the corresponding switch.

	settings	
	Lizenz	
	PDF Manual	
	help F1	
<u>di</u>	splay mode	
🔾 single page		
Output to the second	to be been	
🗌 invert		
🗹 Videoautom	atic But	ton L oder R

s a rule, two-page sheet music always displays 2 pages in parallel. In principle, a 1-sided display is desired, e.g. with small monitors, this can also be set under <u>SERVICE settings</u>.

The note display can also be inverted. The notes then appear in white on a black background. This option should be applied to the display in case of strong light.

Video

For each <u>title</u> a video can be deposited. The videos are always in the directory *VIDEO*.

If there is a video for a <u>title</u>, it will do so in the menu bar with **video** displayed.

Click on this button to test the video playback.

The supported formats are: mp4i.

If you want to start the video with the title call, then **Service-> Settings** to put a hook on **video-automati**c.

Is a 2nd screen or projector connected to the computer, so the video is played on this.

If a video is not played, that's because of the missing codec for this format. The missing codecs can be installed by looking in the **VideoCodec directory** of the program Run the file **STANDARD_Codecs_v651.exe** and then restart the PC.

You can access the PRESETs via **PRESETs** in the menu bar.. Up to 20 presets can be created. If a PRESET is provided with <u>titles</u>, the label of the corresponding button is black. For empty PRESETs the label is gray.



In a PRESET any number of <u>titel</u> can be stored in any order. The order can be changed at any time, as well as the content of a PRESET. To edit a PRESET, right-click on the corresponding preset or select the desired preset with a double-click for editing. Now the PRESET is opened for editing and on the left side all <u>titles</u> of the active <u>titlelist</u> are displayed.



Double-clicking on a <u>title</u> in the <u>titlelist</u> will copy it to the PRESET. It is inserted under the blue marked <u>title</u> in the PRESET. Its position can be changed arbitrarily with the arrow keys. The PRESET can be given a name.

presetr	name change
seret	
title	playtime
6	ca. 15 Min.

The number of tracks contained in the PRESET and the approximate playing time of the entire PRESET are also displayed.



Close will save the PRESET.

To start a PRESET, just click on the corresponding button. Now the first <u>title</u> of the PRESET is called up and the notes are displayed.



next

Via

A click on immediately calls up the next <u>title</u>. So you can put together complete programs in the PRESETs and retrieve as needed.

with back the previous <u>title</u> is called.

If you do not want to start a PRESET with the first <u>title</u>, select the edit mode of the corresponding PRESET and double-click on the desired start <u>title</u>. The PRESET will now be played from the start <u>title</u>.

PRESET copy

To copy a **preset**, drag the **preset** to the new **preset** while holding down the left mouse button. Then the complete content and the name of the **preset** will be copied. All basic settings are made in the **SERVICE-> expanded**. This affects the MIDI settings, the display and the GEMA settings. Likewise, a complete backup can be made and there is the possibility of a remote maintenance by TeamViewer.



Settings <u>Instrument</u> Yamaha Tyros 2 - 5	MIDI-channel M	– settings <u>AIDI-IN device</u> Digital Workstatic		TYROS - Edition
<u>displa</u> o single page o double page invert Videoautomatic	Herein aus an an Article and Article Herein august and article and article Herein automatical and article Herein and Article and Article Herein and Articl		<u>program backup</u>	CLALPHA service@alpha-medialine.de Online Support - click -
			Programmupdate	close

The basic MIDI settings for Keaboard control are in the Program part **SERVICE expanded** made. There, the midi channel is set to connect to the PC. In our case this is the channel 16.

	<u>I - settings</u>
MIDI-channel	MIDI-IN device
16 ~	Digital Workstation-2 \checkmark

In the MIDI / Receive section of the instrument, the MIDI channel 16 / PORT 2 is set to Keyboard.

			MID	I				
s	SYSTEM TI	RANSMIT	RECEIVE	BASS	HORD	DETECT	г м	FC10
	CHANN	IEL	PART	NOTE	CC	PC	PB	AT
	PORT 2	CH9	OFF		_	_	—	
	PORT 2	CH10	OFF	—	-	—	—	—
	PORT 2	CH11	OFF	_	_	—	_	_
	PORT 2	CH12	OFF		_			-
	PORT 2	CH13	OFF		_			
	PORT 2	CH14	OFF		_	_	—	_
	PORT 2	CH15	OFF					
	PORT 2	CH16	KEYBOARD		~	\checkmark		
	D. MONITO	10					_	_
	Rx MONITO	R	1 2 3	4 5 6 7	8 9	10 11 12	2 13 14	15 16
		(MIDI A/	USB 1)					
	PORT 2	(MIDI B/	USB 2)					
				NTROL PR HANGE C				FTER OUCH
	CHANNEL	PAR	Т	~	MARK			

If titleautomatic is used, the MIDI / SYSTEM TRANSMIT CLOCK must be set to ON

				MIDI					
5	SYS	TEM TRA	NSMIT	RECEIVE B	ASS	CHORD D	DETECT	M	FC10
	_			SONG STYLE	M.PAD	LEFT	R1	R2	R3
	1	LOCAL CO	NTROL					\checkmark	
	2	CLOCK:IN7	TERNAL		TRAN	SMIT CLO	DCK:ON	V	
_	-	RECEIVE TH	RANSPOSE	:OFF	START	C/STOP:S	TYLE		
	3	MESSAGE S	337	SYS/EX.		Tx:OFF	7 J	Rx:0I	FF
	3	WESSAGE S	, AA	CHORD SYS/I	EX.	Tx:OFF	7]	Rx:0I	FF
60	NC	OTAL P	MBID			DIGUESI	DIGU	TA 1	
SO		STYLE	M,PAD		EFT	RIGHT1 ON	RIGH		NIGHT3
		OFF	OFF		OFF	OFF	OFF		OFF

he MFC10 commands under MIDI / MFC10 must be configured as follows:

5	SYSTEM TRAN	ISMIT 1	MIDI RECEIVE BASS CHORD	DETECT MFC10
	F	TOOT SWI	TCH SETTING	
	SWITCH NO.	NOTE	FUNCTION	OFF
	0	C#-1	INTRO1	MIDI A — MIDI B —
	1	D-1	INTRO2	USB 1
	2	E⊧-1	INTRO3	USB 2
	3	E-1	MAIN A	
	4	F-1	MAIN B	CH SELECT 15
	5	F*-1	MAIN C	10
	6	G-1	MAIN D	SEND MFC10 SETUP
	I	OOT CON	TROLLER SETTING	51/101
	CONTROLLER NO.	CC	FUNCTION	PART
	1	7	EXPRESSION	RIGHT1
	2	1	OFF	RIGHT1
	3	2	OFF	RIGHT1
			*Mit Ausnahme von STYLE-Pa	irts.

	SYSTEM TRAN		MIDI RECEIVE BASS CHORD	DETECT MFC10		SYSTEM TRAN		MIDI RECEIVE BASS CHORD	DETECT MFC10
			TCH SETTING	MICIO	,			TCH SETTING	Miller Miller
-						SWITCH NO.	NOTE	FUNCTION	OFF
	SWITCH NO.	NOTE	FUNCTION	MIDI A					OFF MIDI A
	6	G-1	MAIN D	MIDI B —		12	C#0	FADE IN/OUT	MIDI B —
	7	Ab-1	FILL BREAK	USB 1		13	D0	MULTI PAD 1	USB 1
	8	A-1	ENDING1	USB 2		14	EP0	MULTI PAD 2	USB 2
	9	B•-1	ENDING2			15	EO	MULTI PAD 3	
	10	B-1	ENDING3	CH SELECT 15		16	F0	MULTI PAD 4	CH SELECT 15
	11	C0	STYLE START/STOP	10		17	F#0	OTS 1	
	12	C#0	FADE IN/OUT	SEND MFC10 SETUP		18	G0	OTS 2	SEND MFC10 SETUP
	I	OOT CON	TROLLER SETTING	UNIOL		1	FOOT CON	TROLLER SETTING	
	CONTROLLER NO.	CC	FUNCTION	PART		CONTROLLER NO.	CC	FUNCTION	PART
	1	7	EXPRESSION	RIGHT1		1	7	EXPRESSION	RIGHT1
	2	1	OFF	RIGHT1		2	1	OFF	RIGHT1
	3	2	OFF	RIGHT1		3	2	OFF	RIGHT1
			*Mit Ausnahme von STYLE-Pa	irts.				*Mit Ausnahme von STYLE-Pa	irts.

YSTEM TRAN		MIDI RECEIVE BASS CHORDI	DETECT MFC10	SYSTEM TRAN		MIDI RECEIVE BASS CHORD I	DETECT MFC10
		TCH SETTING	MPCI0			TCH SETTING	
SWITCH NO.	NOTE	FUNCTION	OFF	SWITCH NO.	NOTE	FUNCTION	OFF 🔼
18	G0	OTS 2	MIDI A MIDI B	23	C1	MODULATION(ALT) RIGHT3	MIDIA U
19	A۶O	OTS 3	USB 1 📥	24	C#1	SUSTAIN	USB 1
20	A0	OTS 4	USB 2	25	D1	BASS HOLD	
21	BFO	MODULATION(ALT) RIGHT1		26	Eb1	VOCAL HARMONY	CH CELECT
22	B0	MODULATION(ALT) RIGHT2	CH SELECT 15	27	E1	VOCAL EFFECT	CH SELECT 15
23	C1	MODULATION(ALT) RIGHT3		28	F1	SYNCHRO START	
24	C#1	SUSTAIN	SEND MFC10 SETUP	29	F#1	FILL SELF	SEND MFC10 SETUP
ŀ	OOT CON	NTROLLER SETTING		1	OOT CO	NTROLLER SETTING	
CONTROLLER NO.	CC	FUNCTION	PART	CONTROLLER NO.	CC	FUNCTION	PART
1	7	EXPRESSION	RIGHT1	1	7	EXPRESSION	RIGHT1
2	1	OFF	RIGHT1	2	1	OFF	RIGHT1
3	2	OFF	RIGHT1	3	2	OFF	RIGHT1
		*Mit Ausnahme von STYLE-Pa	rts.			*Mit Ausnahme von STYLE-Pa	rts.

With a click on *program update* in the **expanded area** is checked automatically whether a new program version is available for download on the Internet.



The new version of the program can then be downloaded from the Internet by clicking **Start Update**. The prerequisite is, of course, that the PC is connected to the Internet. equipment

footswich

footswich

Bluetooth

USB



PageFlip Dragon



This foot switch - PageFlip Dragon - can be connected via Bluetooth as well as via USB. It is freely programmable via Bluetooth. If the footswitch is to be used only for turning pages, So the type - PageFlip Firefly - which can also be connected via Bluetooth is sufficient. The footswitches are also preprogrammed for *ATMObyte*® *TYROS-Edition* and offered with the software.

With the PageFlip Dragon it is e.g. possible and can be programmed by yourself:

Select title (F6 and F7 on the title selection page) Call up a track or leave the note display (ENTER)

Seite 60 von 68

Page flip (F6 and F7 on note display) Continue registration (F4 and F5 on the note display) play different Tusch's (F4 and F5 on the title selection page) etc.

If you have further questions, contact the manufacturer of *ATMObyte® TYROS-Edition* (info@alpha-medialine.de).



USB

Function in the program part Notes: Left foot key: Title list scroll backward Right foot key: Title list scroll forward Middle foot key: Call up titles

<u>Function for note display:</u> <u>Left foot key: to scroll backwards to the previous track or notes</u> <u>Right foot key: scroll forward through the next track or notes</u> <u>Middle footswitch: start sound or next track</u>

Thus, the software is also very suitable for musicians who do not use a keyboard but want to access a large pool of notes in the computer, e.g. Accordion player or sax player etc.

If the footswitch is only needed to turn the notes, a 2-button footswitch is also available. The foot switches are preprogrammed for *ATMObyte*® *TYROS-Edition* and offered with the software. AKcontrol can run on all Windows systems as of Win XP, even under Win 10.

On MAC systems AKcontrol also runs, but VMware Fusion must be installed beforehand.

There is no special power required from the PC. The standard computers offered today meet the requirements of the software.

> ALL IN ONE PC's are best suited with a touch screen. You only have one device. These PCs are available in different sizes.

For a fixed installation on your home keyboard, this can be a bit bigger screen, about 23 ".

On the go, a tablet, netbook, transbook or notebook of about 13 "is enough.

To use the internal help documentation), there are 2 possibilities. The first option is to press the *F1 key* on the keyboard. The second possibility is the call via **Service-> Help** in the menu bar.



How can I simulate the right mouse button with a finger on a touch display?

Very easily.

Leave your finger on the desired position of the display (about 1 second), until a mark becomes visible around the finger (Win7 a square, Win8 and Win10 a circle). This basically applies under Windows and not only for *ATMObyte® TYROS-Edition*.

remote maintenance

In the area **SERVICE-> expanded** can with a Click on remote maintenance to connect to the internet. It then starts the remote maintenance program TEAMVIEWER. This allows direct help via the Internet.



Instrument MIDI-channel MIDI-IN device Yamaha Tyros 2 - 5 16 V Digital Workstation-2 V	TYROS - Edition
O single page	
invert Image: State of the	CALPHA service@alpha-medialine.de Online Support - click -

Enter comments in sheet music

The existing PDF notes in ATMObyte can easily be supplemented with additional comments, etc.

Select the title, but do not call the notes yet and press F10 on the PC keyboard.

Now the PDF file with the notes is opened with the PDF program, which is set as the default program under Windows.

In general, this is e.g. the free **Acrobat Reader**. More recommendable is the free program **FOXIT READER**. Of course, any other PDF program can be used with the edit function.